

## Relocating the iTracker® to a New Site

When transferring an iTracker from one location to another, it is necessary to implement the following procedure so that the new operating parameters can be securely initiated. Connect to the iTracker using the instructions outlined in the IOM on Page 7, Paragraphs 3-5. Upon successful connection, the “Live Value” page will appear. Click on “Settings” on the bottom of your screen and the “iTracker Setup” page will appear as pictured below.

In the “Site Name” box, write in the new location name and click on “New”. A screen (below right) will appear asking “are you sure you want to proceed?” If the answer is “OK”, all of the historical data files from the previous site will be deleted. You are now ready to begin the calibration procedure for a new site. **Please make sure to click on the “Save” button each time a change on the “iTracker Setup” page is initiated.**

The screenshot shows the iTracker Setup page on a mobile device. The page has a blue header with the iTracker logo and the title "iTracker Setup". Below the header, there are several input fields and buttons. The "Site Name" field contains "Site 01" and a yellow "New" button is to its right. Below this, there are two rows of fields: "Pipe ID" with the value "8" and "Damping" with the value "3"; "Log Interval(min.)" with the value "1" and "Units of Measure" with the value "English"; and "Population" with the value "100". A yellow "Save" button is located below these fields. At the bottom of the form, there is a "Date/Time" field showing "10/04/2016 14:11:06" and a yellow "Sync" button. Below that is a "Level" field and a yellow "Send" button. The bottom navigation bar has four tabs: "Live", "History", "Logs", and "Settings".

The screenshot shows the iTracker Setup page on a mobile device with a confirmation dialog box overlaid. The dialog box has a white background and contains the text: "www.eastechiq.com says: New Site clears calibration, log data, and deltaVs. Are you sure you want to proceed?". Below this text is a checkbox labeled "Prevent this page from creating additional dialogs". At the bottom of the dialog are two buttons: "CANCEL" and "OK". The background of the page is dimmed, showing the "iTracker Setup" page with a greyed-out "New" button. The date/time field now shows "10/04/2016 15:33:21". The bottom navigation bar remains the same.